



4 PATCH STOCKING



MAYWOOD  STUDIO

4 PATCH STOCKING

GLITZ FABRIC FROM MAYWOOD STUDIO

FABRIC

Yardage - All Fat Quarters



Red

MASGLI-REB (1 FQ)



Green

MASGLI-GRB (1 FQ)



Black

MASGLI-BLB (1 FQ)



White

MASGLI-SIW (1 FQ)



Backing

MASBLM (1 FQ)

Lining

Your Choice (2 FQs)

CUTTING

Red

Cut (24) 2-1/2" squares

Green

Cut (6) 1" x 20" strips for strip sets

Green

Cut (4) 1-1/2" strips into:
(46) 1-1/2" squares

White

Cut (6) 1" x 20" strips for strip sets

Cut (2) 5-1/2" x 16-1/2"
& (1) 5-1/2" x 1-1/2" pieces for cuffs

Backing

Cut (1) 13" x 21"

Lining

Cut from Two Fat Quarters
(2) 13" x 21"

CONSTRUCTION

An accurate 1/4" seam allowance is imperative. Take time to do a seam allowance check before beginning. Cut TWO pieces of fabric exactly 1-1/2" x 4". Stitch them together with a 1/4" seam. Press in either direction. At the midpoint along this unit, measure across. It should be 2-1/2". If not, adjust your seam and repeat until you are correct.


This stocking finishes 8" wide. The piecing, when accurate, will allow you to place the pattern on the patchwork, nearly exactly. Should your piece be too small because of large seams you may either add a small strip along the edge OR trim the stocking pattern a wee bit to make it fit,

The Stocking shaped pattern is available full size as a separate download named Stocking Template.


1. Stitch (5) strip sets of 1" Green and 1" White. Press toward the Green. They should measure 1-1/2" wide from raw edge to raw edge. From these strip sets, subcut (92) 1" units.




2. Place TWO of the Step 1 subcuts right sides together, opposite colors touching, nesting their seams. Join with a 1/4" seam to form a 1-1/2" raw edge to raw edge Four-patch unit. Press as desired. Make (46).




3. Positioned as shown, stitch each Step 2 Four-patch unit to a 1-1/2" square of Black. Direct the seam toward the Black. Make (46).




4. Join TWO of the Step 3 units right sides together, oppositely, nesting their seams. Press as desired. Make (23).




5. Use the Step 4 units and the (24) 2-1/2" squares of Red to lay out the Stocking Front patchwork. Stitch it together, taking care to maintain accuracy. Alternate the seams. Press carefully – very flat. The narrow part should be 8-1/2" wide, raw edge to raw edge. The vertical measurement is 20-1/2" raw edge to raw edge.



6. Position the Stocking pattern on the patchwork and cut the shape.




7. Place the Stocking pattern upside down on the right side of a 13" x 21" Backing. Cut a Stocking back in mirror image to the front.




8. In the same manner cut (2) mirror image Stocking patterns from (2) 13" x 21" Lining pieces.

9. Right sides together, stitch the Stocking front and back together, leaving open at the upper edge. Clip the seams to the stitching line carefully in the curved areas. Turn right side out and finger press.

10. Right sides together, stitch the Lining front and back together, except . . . along the long 'back' seam, stitch about 4" from the top. Leave 6" 'open' for turning later. Continue stitching around the heel, toe and back to the top. Leave this piece inside out.



11. Place the (2) Cuff pieces which measure 5-1/2" x 16-1/2" right sides together. Draw a pencil line 1/4" above the lower edge, and another line 1-1/4" above the lower edge. These two lines will be 1" apart.



12. Beginning at one side of the upper line, measure in 1/4" and make a dot. Make additional dots every 2". The final dot should be 1/4" from the other side.

13. Beginning at one side of the lower line, measure 1-1/4" and make a dot. Make additional dots every 2". The final dot should be 1-1/4" from the other side.

14. Connect the dots, forming a zig-zag pattern.

15. Keeping the two pieces precisely together, shorten your stitch length and stitch the zig-zag from dot to dot, beginning at a dot (NOT the raw edge 1/4" away) and ending at the final upper dot.

16. Cut the shape, leaving a narrow 1/8" seam allowance. Clip a bit closer to the seam on the upper dots.

17. Carefully turn right side out and taking care to not poke through the stitching, make the points look right. Press carefully.

18. Keeping the points out of the way, open it and place the side seams together, right sides together. A 1/4" seam along the side will close the cuff, and just skim past the points. Finger press this seam open. Turn right side out. It will be a 16" tube with a facing and points along the finished edge. The upper edge will be open.

19. Slide the Step 18 cuff over the outside of the right side out stocking. Pin in place with all the upper raw edges even.

20. Make a loop to hang the stocking from the 1-1/2" x 5-1/2" Cuff fabric. Fold both long edges toward the center, then fold that in half and stitch along the edge. Make certain it is right side out when stitched.

21. Fold the Step 20 loop in half. Match the raw edges to the raw edges of the top of the Stocking and pin in place.
22. Gently stuff the Step 19 Stocking inside the wrong side out Lining. Match the upper raw edges, taking care to have the toe heading the same direction on both pieces. Pin. Stitch around the upper edge.
23. Carefully pull the Stocking through the 6" opening you left in the Lining. Close the Lining opening by folding the seams to the inside, matching the folds, and stitching very close to the folded seams.
24. Stuff the Lining into the stocking. Shape the Cuff so it folds over the top of the Stocking, exposing the loop.



25. Embellish the Stocking, Cuff, or both. Enjoy!

Stocking Template 50% of actual size. Print or copy at 200% to get actual size.

